

Generalization of the Dependent Function in Extenics for Nested Sets with Common Endpoints to 2D-Space, 3D-Space, and generally to n-D-Space

Florentin Smarandache
University of New Mexico
Mathematics and Science Department
705 Gurey Ave.
Gallup, NM 87301, USA
E-mail: smarand@unm.edu

Abstract.

In this paper we extend Prof. Yang Chunyan and Prof. Cai Wen's dependent function of a point P with respect to two nested sets $X_0 \subset X$, for the case the sets X_0 and X have common ending points, from 1D-space to n -D-space. We give several examples in 2D- and 3D-spaces. When computing the dependent function value $k(\cdot)$ of the optimal point O , we take its maximum possible value.

Formulas for computing $k(O)$, and the geometrical determination the Critical Zone are also given.

1. **Principle of Dependent Function** of a point $P(x)$ with respect to a nest of two sets $X_0 \subset X$, i.e. *the degree of dependence of point P with respect to the nest of the sets $X_0 \subset X$* , is the following.

The dependent function value, $k(x)$, is computed as follows:

- *the extension distance between the point P and the larger set's closest frontier, divided by the extension distance between the frontiers of the two sets {both extension distances are taken on the line/geodesic that passes through the point P and the optimal/attracting point O };*
- *the dependent function value is positive if point P belongs to the larger set, and negative if point P is outside of the larger set.*

2. **Dependent Function Formula for nested sets having common ending points in 1D-Space.**

For two nested sets $X_0 \subset X$ from the one-dimensional space of real numbers R , with X_0 and X having common endpoints, the **Dependent Function** $K(x)$, which gives the degree of dependence of a point x with respect to this pair of included 1D-intervals, was defined by Yang Chunyan and Cai Wen in [2] as:

$$K(x) = \begin{cases} \frac{\rho(x, X)}{\rho(x, X) - \rho(x, X_0)} & \rho(x, X) - \rho(x, X_0) \neq 0, x \in X \\ -\rho(x, X_0) + 1 & \rho(x, X) - \rho(x, X_0) = 0, x \in X_0 \\ -\rho(x, X) & \rho(x, X) - \rho(x, X_0) = 0, x \notin X_0, x \in X \\ \frac{\rho(x, X)}{\rho(x, X) - \rho(x, \hat{X})} & \rho(x, X) - \rho(x, \hat{X}) \neq 0, x \in R - X \\ -\rho(x, \hat{X}) - 1 & \rho(x, X) - \rho(x, \hat{X}) = 0, x \in R - X \end{cases} \quad (1)$$

where $X_0 = \langle a_0, b_0 \rangle$, $X = \langle a, b \rangle$, $\hat{X} = \langle c, d \rangle$, and $X_0 \subset X \subset \hat{X}$.

3. n -D-Dependent Function Formula for two nested sets having no common ending points.

The extension n -D-dependent function $k(\cdot)$ of a point P , which represents the degree of dependence of the point P with respect to the nest of the two sets $X_0 \subset X$, is:

$$k(P) = \frac{\rho(P, \text{BiggerSet})}{\rho(P, \text{BiggerSet}) - \rho(P, \text{SmallerSet})} = \frac{\rho_{nD}(P, X)}{\rho_{nD}(P, X) - \rho_{nD}(P, X_0)} = \pm \frac{|PP_2|}{|PP_2| - |PP_1|} = \pm \frac{|PP_2|}{|P_1P_2|} \quad (2)$$

In other words, the extension n -D-dependent function $k(\cdot)$ of a point P is the n -D-extension distance between the point P and the closest frontier of the larger set X , divided by the n -D-extension distance between the frontiers of the two nested sets X and X_0 ; all these n -D-extension distances are taken along the line (or geodesic) OP .

4. n -D-Dependent Function Formula for two nested sets having common ending points.


We generalize the above formulas (1) and (2) to an **n -D Dependent Function** of a point $P(x_1, x_2, \dots, x_n)$ with respect to the nested sets X_0 and X having common endpoints, $X_0 \subset X$, from the universe of discourse U , in the n -D-space:

$$K_{nD}((x_1, x_2, \dots, x_i)) = \begin{cases} \frac{\rho_{nD}((x_1, x_2, \dots, x_i), X)}{\rho_{nD}((x_1, x_2, \dots, x_i), X) - \rho_{nD}((x_1, x_2, \dots, x_i), X_0)} & \rho_{nD}((x_1, x_2, \dots, x_i), X) - \rho_{nD}((x_1, x_2, \dots, x_i), X_0) \neq 0, (x_1, x_2, \dots, x_i) \in U \\ -\rho_{nD}((x_1, x_2, \dots, x_i), X_0) + 1 & \rho_{nD}((x_1, x_2, \dots, x_i), X) - \rho_{nD}((x_1, x_2, \dots, x_i), X_0) = 0, (x_1, x_2, \dots, x_i) \in X_0 \\ -\rho_{nD}((x_1, x_2, \dots, x_i), X) & \rho_{nD}((x_1, x_2, \dots, x_i), X) - \rho_{nD}((x_1, x_2, \dots, x_i), X_0) = 0, (x_1, x_2, \dots, x_i) \in U - X_0 \end{cases} \quad (3)$$

5.1. Example 1 of nested rectangles with one common side.

We have a factory piece whose desired 2D-dimensions should be $20 \text{ cm} \times 30 \text{ cm}$, and acceptable 2D-dimensions $22 \text{ cm} \times 32 \text{ cm}$, but the two rectangles have common ending points. We define the

extension 2D-distance, and then we compute the extension 2D-dependent function. Let's do an extension 2D-diagram:



The Critical Zone in the top, down, and left sides of the Diagram 1 as the same as for the case when the two pink and black rectangles have no common ending points. But on the right-hand side the Critical Zone is delimited by the a blue curve in the middle and the blue dotted lines in the upper and lower big rectangle's corners.

The dependent function of the points Q, Q_1, Q_2 is respectively:

$$k(Q) = |QQ_1| + 1, \text{ and } k(Q_1) = 1 \text{ (if } Q_1 \in A'B'C'D') \text{ or } 0 \text{ (if } Q_1 \notin A'B'C'D'), \text{ and } k(Q_2) = -|Q_2Q_1| = -1, \text{ (4)}$$

where $|MN|$ means the geometrical distance between the points M and N .

The dependent function of point P is normally computing:

$$k(P) = \frac{|PP_2|}{|P_1P_2|}. \quad (5)$$

5.2. Example 2 of nested rectangles with two common sides.




Diagram 2.

We observe that the Critical Zone changes dramatically in the places where the common ending points occur, i.e. on the top and respectively left-hand sides. The Critical Zone is delimited by blue curves and lines on the top and respectively left-hand sides.

Now, the dependent function of point P is different from the Diagram 1:

$$k(P) = |PP'| + 1. \tag{6}$$


The dependent function of the optimal point O should be the maximum possible value.

Therefore,

$$k(O) = \max \{ |OT_1| + 1, |OT_2| + 1, |OP'| + 1, |OC'| + 1, \frac{|OT_7|}{|T_6T_7|}, \frac{|OT_5|}{|T_4T_5|}, \frac{|OA|}{|T_3A|}, \text{etc.} \}. \tag{7}$$

5.3. Example 3 of nested circles with one common ending point.

Assume the desirable circular factory piece radius is 6 cm and acceptable is 8 cm, but they have a common ending point P' .



The Critical Zone is between the green and blue circles, together with the blue line segment $P''P'$ (this line segment resulted from the fact the P' is a common ending point of the red and green circles).

The dependent function values for the following points are:

$$k(P) = |PP'| + 1; \tag{8}$$

$$k(P') = 1 \text{ (if } P' \text{ belongs to the red circle), or } 0 \text{ (if } P' \text{ does not belong to the red circle);} \tag{9}$$

$$k(P'') = |P''P'|; \tag{10}$$

$$k(O) = \max \left\{ |OP'| + 1; \frac{|OT_4|}{|T_3T_4|} \right\}, \tag{11}$$

where T_3 lies arbitrary on the red circle, but $T_3 \neq P'$, and T_4 lies on the green circle but T_4 belongs to the line (or geodesic) OT_3 .

5.4. Example 4 of nested triangles with one common bottom side.




Diagram 4.

The Critical Zone is between the green and blue dotted triangle to the left-hand and right-hand sides, while at the bottom side the Critical Zone is delimited by the blue curve in the middle and the blue small oval triangles $A''AA'$ and respectively $B''BB'$.

The dependent function values of the following points are given below:

$$k(P) = \frac{|PP''|}{|P'P''|} > 1; k(P')=1; k(P'')=0; k(P''') = -1. \quad (12)$$

$$\text{Similarly: } k(Q) = \frac{|QQ''|}{|Q'Q''|} > 1; k(Q')=1; k(Q'')=0; k(Q''') = -1. \quad (13)$$

With respect to the bottom common side (where the line segment AB lies on line segment $A'B'$) one has:

$$k(T) = |TS''|+1; k(S'') = 1 \text{ (if } S'' \text{ belongs to the red triangle } ABC), \text{ or } 0 \text{ (if } S'' \text{ does not belong to the red triangle } ABC); k(S) = |SS''|; k(S') = -1. \quad (14)$$

$$k(O) = \max \left\{ \max_{S'' \in [AB]} (|OS''| + 1); \max_{\substack{P' \in [AC] \cup [CB], P'' \in [A'C'] \cup [C'B'] \\ P \in OP'' \\ OPP'' \text{ line/geodesic}}} \left(\frac{|OP''|}{|P'P''|} \right) \right\}. \quad (15)$$

5.5. Example 5 in 3D-Space of two prisms having a common face.




Diagram 5.

The Critical Zone (the zone where the extension dependent function takes values between 0 and -1) envelopes the larger green prism $ABCDEFGH$ at an equal distance from it as the distance between the red prism $A'B'C'D'E'F'G'H'$ and the green prism $ABCDEFGH$ with respect to the faces $ABCD$, $ADHE$, $BCGF$, $EFGH$, and $ABFE$ (because these green faces and their corresponding

red faces $A'B'C'D'$, $A'D'H'E'$, $B'C'G'F'$, $E'F'G'H'$, and respectively $A'B'F'E'$ have no common points).

But the green face $DCGH$ contains the red face $D'C'G'H'$, therefore for all their common points (i.e. all points inside of and on the rectangle $D'C'G'H'$) the extension dependent function has wild values. $D'C'G'H'$ entirely lies on $DCGH$. The Critical Zone related to the right-hand green face $DCGH$ and the red face $D'C'G'H'$ is the solid bounded by the blue continuous and dashed curves on the right-hand side.

In general, let's consider two n -D sets, $S_1 \subset S_2$, that have common ending points (on their frontiers). Let's note by C_E their common ending point zone. Then:

The Dependent Function Formula for computing the value of the Optimal Point O is

$$k(O) = \max \left\{ \max_{S'' \in C_E} (|OS''| + 1); \max_{\substack{P' \in Fr(S_1 - C_E), P'' \in Fr(S_2 - C_E) \\ P' \in OP'' \\ OPP'' \text{ line/ geodesic}}} \left(\frac{|OP''|}{|P'P''|} \right) \right\}. \quad (16)$$

We can define the Critical Zone in the sides where there are common ending points as:

$$Z_{C1} = \{P(x) | P \in U-S_2, 0 < d(P, P'') \leq 1, P'' \in Fr(S_1) \cap Fr(S_2) \text{ and } P'' \in OP\}, \quad (17)$$

where $d(P, P'')$ is the classical geometrical distance between the points P and P'' .

And for the sides which have no common ending points, the Critical Zone is:

$$Z_{C2} = \{P(x) | P \in U-S_2, 0 < d(P, P'') \leq d(P''P'), \text{ where } P'' \in Fr(S_2) \text{ and } P' \in Fr(S_1) \text{ and } P'' \in OP\}. \quad (18)$$

$$\text{Whence, the total Critical Zone is: } Z_C = Z_{C1} \cup Z_{C2}. \quad (19)$$

References:

- [1] Cai Wen. Extension Set and Non-Compatible Problems [J]. Journal of Scientific Exploration, 1983, (1): 83-97.
- [2] Yang Chunyan, Cai Wen. Extension Engineering [M]. Beijing: Public Library of Science, 2007.
- [3] F. Smarandache, Generalizations of the Distance and Dependent Function in Extenics to 2D, 3D, and n -D, viXra.org, <http://vixra.org/abs/1206.0014> and <http://vixra.org/pdf/1206.0014v1.pdf>, 2012.
- [4] F. Smarandache, V. Vlădăreanu, Applications of Extenics to 2D-Space and 3D-Space, viXra.org, <http://vixra.org/abs/1206.0043> and <http://vixra.org/pdf/1206.0043v2.pdf>, 2012.